

What does mean the error NO X11 DISPLAY?

Author: Veryant Support

Saved From: <http://support.veryant.com/support/phpkb/question.php?ID=207>

The error NO X11 DISPLAY means that for some reason isCOBOL try to access AWT/SWING GUI Interface and your system have not that.

If your cobol program have not any GUI interface included, you can try to set the java.awt.headless=true property on your run command:

```
iscrun -J-Djava.awt.headless=true .....
```

or

```
java -Djava.awt.headless=true .....
```

If your cobol program include some textual ACCEPT/DISPLAY you need to turn on isCOBOL CHARVA support adding -t option:

```
iscrun -J-Djava.awt.headless=true -t .....
```

or using the property

iscobol.guifactory.class=com.iscobol.gui.client.charva.GuiFactoryImpl with java:

```
java -Djava.awt.headless=true -Discobol.guifactory.class=com.iscobol.gui.client.charva.GuiFactoryImpl
```