

## How do I determine what properties are set?

To discover what property settings are being used during local execution of a program on Windows, you can set `iscobol.tracelevel=1` (or 3, 7, 15, etc) and set `iscobol.logfile` to the path and name of a file. You will see a trace of places where the runtime found properties and also the resulting property settings:

```
Mar 23, 2012 15.06.11.529 INFO: [CONFIG] [isCobol] iscobol.properties.sources= /e
tc/iscobol.properties From class path: C:/Users/dlubin/workspace_abc/project1/res
ources/iscobol.propertiesMar 23, 2012 15.06.11.529 INFO: [CONFIG] [isCobol] iscobol.log
file=../logs/log.txtMar 23, 2012 15.06.11.529 INFO: [CONFIG] [isCobol] iscobol.tracelev
el=15Mar 23, 2012 15.06.11.530 INFO: [CONFIG] [isCobol] iscobol.file.prefix=../dataMar
23, 2012 15.06.11.530 INFO: [CONFIG] [isCobol] iscobol.font.small=Microsoft Sans Serif-
08Mar 23, 2012 15.06.11.611 INFO: ENTER PROGRAM 'PROGRAM1' {Mar 23, 2012 15.06.11.612 I
NFO: ENTER PARAGRAPH 'MAIN' [PROGRAM1]Mar 23, 2012 15.06.11.613 INFO: EXIT PARAGRAPH 'M
AIN' [PROGRAM1]Mar 23, 2012 15.06.11.613 INFO: EXIT PROGRAM 'PROGRAM1' }
```

For example,

Outside the IDE you can add these settings with `-J-D` options as in the following:

```
isrun -J-Discobol.tracelevel=15 -J-Discobol.logfile=log.txt PROGRAM
```

Or you can add them to the properties file you specify on the command line as in:

```
isrun -c config.properties PROGRAM or isrun -J-Discobol.conf=config.properties PROGRAM
```

Inside the IDE you can add these settings in the "Run configuration" you are executing. To do this, select `Run > Run Configurations...`, select your run configuration and type the following into the System properties field:

```
-Discobol.tracelevel=15 -Discobol.logfile=../logs/log.txt
```

Or if you are not executing with a "Run configuration" then you can add these to the project's `resourcesiscobol.properties` file or other `iscobol.properties` file in your class path, or a file you have specified in the `Project Properties > Settings > Compile/Runtime options Runtime` tab with `-Discobol.conf=config.properties`, or you can add the following directly to the System properties field:

```
-Discobol.tracelevel=15 -Discobol.logfile=../logs/log.txt
```

Note that the trace file log.txt will be created in the logs folder relative to the parent folder of the working directory during execution. If your working directory is set to "output" as is the default then ../logs/log.txt will appear in the project's logs folder. You may need to right-click on the logs folder and select Refresh to see the log.txt file appear in the File view.

The reason that the IDE uses the properties in resourcesiscobol.properties is that it adds ../resources to the class path by default whenever you run a program, and class path is one of the places that isCOBOL looks for properties files.

See also [What is the recommended method for specifying isCOBOL framework properties?](#)

Online URL: <https://support.veryant.com/support/phpkb/article.php?id=193>